

# Concurrent Systems

## 8L for Part IB

Handout 2

Dr. Steven Hand

1

## Event Counts & Sequencers

- Alternative synchronization scheme (1979)
- **Event Counts**: a special type of variable
  - Essentially an increasing integer, initialized to zero
- Supports three operations:
  - int **advance**(ec) { ec.val++; return ec.val; }
  - int **read**(ec) { return ec.val; }
  - void **await**(ec, v) { sleep until ec.val >= v; return }
- Can be somewhat lazy
  - **read()** can provide a stale value
  - **await()** can be a little “late”, i.e. (ec.val-v) can be > 0

2

## Event Counts: Producer-Consumer

```
int buffer[N]; int in = 0, out = 0;
CEV = new EventCount(); // counts no of “consumptions”
PEV = new EventCount(); // counts no of “productions”
```

```
// producer thread
while(true) {
    item = produce();
    await(CEV, (in-N)+1);
    buffer[in % N] = item;
    in = in + 1;
    advance(PEV);
}
```

```
// consumer thread
while(true) {
    await(PEV, out+1);
    item = buffer[out % N];
    out = out + 1;
    advance(CEV);
    consume(item);
}
```

- Very similar to semaphore solution (although free running counters ... problem?)
- Again, no **explicit** mutual exclusion

3

## Sequencers

- To complete the picture, add **Sequencers**
  - Special type of variable: an integer initialized to 0
- Has just one operation:
  - int **ticket**(seq) { v = seq.val; seq.val++; return v; }
  - atomically produces a unique (increasing) value
- Can use an event count & a sequencer together to implement a mutual exclusion lock:

```
LOCK(L) {
    turn = ticket(L.SQ);
    await(L.EV, turn);
}
```

```
UNLOCK(L) {
    advance(L.EV);
}
```

4

## Generalized Producer-Consumer

```
int buffer[N];
PEV = new EventCount(); CEV = new EventCount();
PSQ = new Sequencer(); CSQ = new Sequencer();
```

```
// producer threads
while(true) {
    item = produce();
    turn = ticket(PSQ);
    await(PEV, turn);
    await(CEV, (turn-N)+1);
    buffer[turn % N] = item;
    advance(PEV);
}
```

```
// consumer threads
while(true) {
    turn = ticket(CSQ);
    await(CEV, turn);
    await(PEV, turn+1);
    item = buffer[turn % N];
    advance(CEV);
    consume(item);
}
```

- Safe concurrent access by any { producer , consumer } pair
- A single **advance()** invocation provides both mutual exclusion & condition synchronization

5

## Event Counts & Sequencers: Summary

- A different scheme than semaphores
  - Basic primitives are synchronization & ordering
  - (tho can be used to build mutual exclusion)
- Lazy semantics allow efficient implementation
  - Originally designed for multiprocessors
- Can lead to simpler [well, shorter] code...
  - But still pretty low-level and hard to use
  - (convince yourself all the examples are correct;-)
- A higher-level paradigm would be nice!

7

## Event Counts & Sequencers: MRSW

```
WEV = new EventCount(); // counts no of updates (writes)
WSQ = new Sequencer(); // for writer mutual exclusion
REV = new EventCount(); // 'version' of data
```

```
// a writer thread
advance(REV);
turn = ticket(WSQ);
await(WEV, turn);
.. perform update to data
advance(WEV);
```

```
// a reader thread
do {
    v1 = read(REV);
    await(WEV, v1);
    .. read data
    v2 = read(REV);
} while(v1 != v2);
```

- Core of writer is mutual exclusion (WSQ, WEV)
- Q: why does reader need to **await()**?

6

## Conditional Critical Regions

- One early (1970s) effort was CCRs
  - Variables can be explicitly declared as 'shared'
  - Code can be tagged as using those variables, e.g.

```
shared int A, B, C;
region A, B {
    await( /* arbitrary condition */ );
    // critical code using A and B
}
```

- Compiler automatically declares and manages underlying primitives for mutual exclusion or synchronization
  - e.g. wait/signal, read/await/advance, ...
- Easier for programmer (c/f previous implementations)

8

## CCR Example: Producer-Consumer

```
shared int buffer[N];
shared int in = 0; shared int out = 0;
```

```
// producer thread
while(true) {
    item = produce();
    region in, out, buffer {
        await((in-out) < N);
        buffer[in % N] = item;
        in = in + 1;
    }
}
```

```
// consumer thread
while(true) {
    region in, out, buffer {
        await((in-out) > 0);
        item = buffer[out % N];
        out = out + 1;
    }
    consume(item);
}
```

- Explicit (scoped) declaration of critical sections
  - automatically acquire mutual exclusion lock on region entry
- Powerful **await()**: any evaluable predicate

9

11

## Monitors

- **Monitors** are similar to CCRs (implicit mutual exclusion), but modify them in two ways
  - Waiting is limited to explicit **condition variables**
  - All related routines are combined together, along with initialization code, in a single construct
- Idea is that **only one thread can ever be executing** ‘within’ the monitor
  - If a thread invokes a monitor method, it will block (queue) if there is another thread active inside
  - Hence all methods within the monitor can proceed on the basis that mutual exclusion has been ensured

## CCR Pros and Cons

- On the surface seems like a definite step up
  - Programmer focuses on **variables** to be protected, compiler generates appropriate semaphores (etc)
  - Compiler can also check that shared variables are never accessed outside a CCR
  - (still rely on programmer annotating correctly)
- But **await(<expr>)** is problematic...
  - What to do if the (arbitrary) <expr> is not true?
  - very difficult to work out when it becomes true?
  - Solution was to leave region & try to re-enter: this is busy waiting, which is very inefficient...

10

## Example Monitor Syntax

```
monitor <foo> {
    // declarations of shared variables

    // set of procedures (or methods)
    procedure P1(...) { ... }
    procedure P2(...) { ... }
    ...
    procedure PN(...) { ... }
}
/* monitor initialization code */
```

All related data and methods kept together

Invoking any procedure causes an [implicit] mutual exclusion lock to be taken

Shared variables can be initialized here

12

## Condition Variables

- Mutual exclusion not always sufficient
  - e.g. may need to wait for a condition to occur
- Monitors allow condition variables
  - Explicitly declared & managed by programmer
  - Support three operations:

```
wait(cv) {
    suspend thread and add it to the queue
    for cv; release monitor lock
}
signal(cv) {
    if any threads queued on cv, wake one;
}
broadcast(cv) {
    wake all threads queued on cv;
}
```

13

## Does this work?

- Depends on implementation of **wait()** & **signal()**
- Imagine two threads, T1 and T2
  - T1 enters the monitor and calls **wait(C)** – this suspends T1, places it on the queue for C, and unlocks the monitor
  - Next T2 enters the monitor, and invokes **signal(C)**
  - Now T1 is unblocked (i.e. capable of running again)...
  - ... but can only have one thread active inside a monitor!
- If we let T2 continue (so-called “signal-and-continue”), T1 must queue for re-entry to the monitor
  - And no guarantee it will be next to enter
- Otherwise T2 must be suspended (“signal-and-wait”), allowing T1 to continue...

15

## Monitor Producer-Consumer Solution?

```
monitor ProducerConsumer {
    int in, out, buf[N];
    condition notfull, notempty;

    procedure produce(item) {
        if( (in-out) == N) wait(notfull);
        buf[in % N] = item;
        if( (in-out) == 0) signal(notempty);
        in = in + 1;
    }

    procedure int consume() {
        if( (in-out) == 0) wait(notempty);
        item = buf[out % N];
        if( (in-out) == N) signal(notfull);
        out = out + 1;
    }
}
/* init */ { in = out = 0; }
```

If buffer is full (in==out+N), must wait for consumer

If buffer was full (in==out), signal the consumer

If buffer is empty (in==out), must wait for producer

If buffer was full before, signal the producer

14

## Signal-and-Wait (“Hoare Monitors”)

- Consider a queue **E** to enter monitor
  - If monitor is occupied, threads are added to **E**
  - May not be FIFO, but should be fair
- If thread T1 waits on C, added to queue **C**
- If T2 enters monitor & signals, waking T1
  - T2 is added to a new queue **S** “in front of” **E**
  - T1 continues and eventually exits (or re-waits)
- Some thread on **S** chosen to resume
  - Only admit a thread from **E** when **S** is empty

16

## Signal-and-Wait Pros and Cons

- We call `signal()` exactly when condition is true, then directly transfer control to waking thread
  - Hence condition will still be true!
- But more difficult to implement...
- And can be difficult to reason about (a call to `signal` *may or may not* result in a context switch)
  - Hence we must ensure that any invariants are maintained at time we invoke `signal()`
- With these semantics, example on p14 is broken:
  - we `signal()` before incrementing in/out

17

## Signal-and-Continue Example

- Consider multiple producer-consumer threads
  1. P1 enters. Buffer is full so blocks on queue for **C**
  2. C1 enters.
  3. P2 tries to enter; occupied, so queues on **E**
  4. C1 continues, consumes, and signals **C** (“notfull”)
  5. P1 unblocks; monitor occupied, so queues on **E**
  6. C1 exits, allowing P2 to enter
  7. P2 fills buffer, and exits monitor
  8. P1 resumes and tries to add item – BUG!
- Hence must *re-test condition*:
  - i.e. `while( (in-out) == N) wait(notfull);`

19

## Signal-and-Continue

- Alternative semantics introduced by Mesa programming language (Xerox PARC)
- An invocation of `signal()` moves a thread from the condition queue **C** to the entry queue **E**
  - Invoking threads continues until exits (or waits)
- Simpler to build... but now not guaranteed that condition is true when resume!
  - Other threads may have executed after the signal, but before you continue

18

## Monitors: Summary

- Structured concurrency control
  - groups together shared data and methods
  - (today we’d call this object-oriented)
- Considerably simpler than semaphores (or event counts), but still perilous in places
- May be overly conservative sometimes:
  - e.g. for MRSW cannot have >1 reader in monitor
  - Typically must work around with entry and exit methods (`BeginRead()`, `EndRead()`, `BeginWrite()`, etc)
- Exercise: sketch a MRSW monitor implementation

20



## Concurrency in Practice

- Seen a number of abstractions for concurrency control
  - Mutual exclusion and condition synchronization
- Next let's look at some concrete examples:
  - Linux kernel
  - POSIX pthreads (C/C++ API)
  - Java
  - C#

21

## Example: Linux Kernel

- Kernel provides spinlocks & semaphores
  - Spinlocks busy wait so only hold for short time
  - (dynamically optimized out on UP kernels)

```
DEFINE_SPINLOCK(mylock);
spin_lock_irqsave(&mylock, flags);
// do stuff (not much!)
spin_lock_irqrestore(&mylock, flags);
```

- Also get *reader-writer* spinlock variants
  - allows many readers or a single writer
  - (mostly deprecated now in favor of RCU)

22

## Example: pthreads

- Standard (POSIX) threading API for C, C++, etc
  - mutexes, condition variables and barriers
- Mutexes are essentially binary semaphores:

```
int pthread_mutex_init(pthread_mutex_t *mutex, ...);
int pthread_mutex_lock(pthread_mutex_t *mutex);
int pthread_mutex_trylock(pthread_mutex_t *mutex);
int pthread_mutex_unlock(pthread_mutex_t *mutex);
```

- A thread calling `lock()` blocks if the mutex is held
  - `trylock()` is a non-blocking variant: returns immediately; returns 0 if lock acquired, or non-zero if not.

23

## Example: pthreads

- Condition variables are Mesa-style:

```
int pthread_cond_init(pthread_cond_t *cond, ...);
int pthread_cond_wait(pthread_cond_t *cond,
                      pthread_mutex_t *mutex);
int pthread_cond_signal(pthread_cond_t *cond);
int pthread_cond_broadcast(pthread_cond_t *cond);
```

- No proper monitors: must manually code e.g.

```
pthread_mutex_lock(&M);
while(!condition)
    pthread_cond_wait(&C, &M);
// do stuff
if(condition) pthread_cond_broadcast(&C);
pthread_mutex_unlock(&M);
```

24

## Example: pthreads

- Barriers: explicit synchronization mechanism
- Wait until all threads reach some point

```
int pthread_barrier_init(pthread_barrier_t *b, ..., N);
int pthread_barrier_wait(pthread_barrier_t *b);

pthread_barrier_init(&B, ..., NTHREADS);
for(i=0; i<NTHREADS; i++)
    pthread_create(..., worker, ...);

worker() {
    while(!done) {
        // do work for this round
        pthread_barrier_wait(&B);
    }
}
```

25

## Example: Java [original]

- Synchronization inspired by monitors
- Objects already encapsulate data & methods!
- Mesa-style, but no explicit condition variables

```
public class MyClass {
    //
    public synchronized void myMethod() throws ...{
        while(!condition)
            wait();
        // do stuff
        if(condition)
            notifyAll();
    }
}
```

- Java 5 provides many additional options...

26

## Example: C#

- Very similar to Java, tho explicit arguments

```
public class MyClass {
    //
    public void myMethod() {
        lock(this) {
            while(!condition)
                Monitor.Wait(this);
            // do stuff
            if(condition)
                Monitor.PulseAll(this);
        }
    }
}
```

- Also provides spinlocks, reader-writer locks, semaphores, barriers, event synchronization, ...

27

## Concurrency Primitives: Summary

- Concurrent systems require means to ensure:
  - **Safety** (mutual exclusion in critical sections), and
  - **Progress** (condition synchronization)
- Seen spinlocks (busy wait); semaphores; event counts / sequencers; CCRs and monitors
- Almost all of these are still used in practice
  - subtle minor differences can be dangerous
  - require care to avoid bugs

28


## Safety and Liveness

- Desirable properties for concurrent systems
  - **Safety**: bad things don't happen
  - **Liveness**: good things (eventually) happen
- Mutual exclusion is primarily about safety
  - Want to ensure two threads don't "collide" in terms of accessing shared data
- ...but may have consequences for liveness too!
  - i.e. must ensure our program doesn't get stuck

29

## Deadlock

- Set of  $k$  threads go asleep and cannot wake up
  - each can only be woken by another who's asleep!
- Real-life example (Kansas, 1920s):
  - "When two trains approach each other at a crossing, both shall come to a full stop and neither shall start up again until the other has gone."
- In concurrent programs, tends to involve the taking of mutual exclusion locks, e.g.:



31

## Liveness Properties

- From a theoretical viewpoint must ensure that we eventually make progress, i.e. want to avoid
  - **Deadlock** (threads sleep waiting for each other), and
  - **Livelock** (threads execute but make no progress)
- Practically speaking, also want good performance
  - **No starvation** (single thread must make progress)
  - (more generally may aim for **fairness**)
  - **Minimality** (no unnecessary waiting or signalling)
- The properties are often at odds with safety :-)

30

## Requirements for Deadlock


- Like all concurrency bugs, deadlock may be rare (e.g. imagine `<cond>` is mostly false)
- In practice there are four necessary conditions
  1. **Mutual Exclusion**: resources have bounded #owners
  2. **Hold-and-Wait**: can get **R<sub>x</sub>** and wait for **R<sub>y</sub>**
  3. **No Preemption**: keep **R<sub>x</sub>** until you release it
  4. **Circular Wait**: cyclic dependency
- Require all four to be true to get deadlock
  - But most modern systems always satisfy 1, 2, 3

32



## Resource Allocation Graphs

- Graphical way of thinking about deadlock
- Circles are threads (or processes), boxes are single owner resources (e.g. mutual exclusion locks)
- A **cycle** means we (will) have deadlock



33


## Dealing with Deadlock

1. Ensure it never happens
  - Deadlock prevention
  - Deadlock avoidance (Banker's Algorithm)
2. Let it happen, but recover
  - Deadlock detection & recovery
3. Ignore it!
  - The so-called "Ostrich Algorithm" ;-)
  - i.e. let the programmer fix it
  - Very widely used in practice!

35

## Resource Allocation Graphs

- Can generalize to resources which can have K distinct users (c/f semaphores)
- Absence of a cycle means no deadlock...
  - but presence only means *may* have deadlock, e.g.



34

## Deadlock Prevention

1. **Mutual Exclusion:** resources have bounded #owners
  - Could always allow access... but probably unsafe ;-)
  - However can help e.g. by using MRSW locks
2. **Hold-and-Wait:** can get **R<sub>x</sub>** and wait for **R<sub>y</sub>**
  - Require that we request all resources simultaneously; deny the request if *any* resource is not available now
  - But must know maximal resource set in advance = hard?
3. **No Preemption:** keep **R<sub>x</sub>** until you release it
  - Stealing a resource generally unsafe (tho see later)
4. **Circular Wait:** cyclic dependency
  - Impose a partial order on resource acquisition
  - Can work: but requires programmer discipline


36

## Example: Dining Philosophers

- 5 philosophers, 5 forks, round table...

```
Semaphore forks[] = new Semaphore[5];

while(true) { // philosopher i
    think();
    wait(fork[i]);
    wait(fork[(i+1) % 5]);
    eat();
    signal(fork[i]);
    signal(fork[(i+1) % 5]);
}
```



- Possible for everyone to acquire 'left' fork (i)
  - Q: what happens if we swap order of **signal**(s)?


37

## Example: Dining Philosophers

- (one) Solution: always take lower fork first

```
Semaphore forks[] = new Semaphore[5];

while(true) { // philosopher i
    think();
    first = MIN(i, (i+1) % 5);
    second = MAX(i, (i+1) % 5);
    wait(fork[first]);
    wait(fork[second]);
    eat();
    signal(fork[second]);
    signal(fork[first]);
}
```



- Now even if 0, 1, 2, 3 are held, 4 will not acquire final fork

38

## Deadlock Avoidance

- Prevention aims for deadlock-free “by design”
- **Deadlock Avoidance** is a dynamic scheme:
  - Assume we know maximum possible resource allocation for every process / thread
  - Track actual allocations in real-time
  - When a request is made, only grant if guaranteed no deadlock even if all others take max resources
- e.g. Banker’s Algorithm – see textbooks
  - Not really useful in general as need *a priori* knowledge of #processes/threads, and their max resource needs

39

## Deadlock Detection

- A dynamic scheme which attempts to determine if deadlock exists
- When only a single instance of each resource, can explicitly check for a cycle:
  - Keep track which object each thread is waiting for
  - From time to time, iterate over all threads and build the resource allocation graph
  - Run a cycle detection algorithm on graph  $O(n^2)$
- More difficult if have multi-instance resources

40

## Deadlock Detection

- Have  $m$  distinct resources and  $n$  threads
- $V[0:m-1]$ , vector of available resources
- $A$ , the  $m \times n$  resource allocation matrix, and  $R$ , the  $m \times n$  (outstanding) request matrix
  - $A_{ij}$  is the number of objects of type  $j$  owned by  $i$
  - $R_{ij}$  is the number of objects of type  $j$  needed by  $i$
- Proceed by marking rows in  $A$  for threads that are not part of a deadlocked set
  - If we cannot mark all rows of  $A$  we have deadlock

41

## Deadlock Detection Algorithm

- Mark all zero rows of  $A$  (since a thread holding zero resources can't be part of deadlock set)
- Initialize a working vector  $W[0:m-1]$  to  $V$
- Select an unmarked row  $i$  of  $A$  s.t.  $R[i] \leq W$ 
  - (i.e. find a thread whose request can be satisfied)
  - Set  $W = W + A[i]$ ; mark row  $i$ , and repeat
- Terminate when no such row can be found
  - Unmarked rows (if any) are in the deadlock set

42

## Deadlock Detection Example 1

- Five threads and three resources (none free)

	A			R			V			W		
	X	Y	Z	X	Y	Z	X	Y	Z	X	Y	Z
T0	<del>0</del>	<del>1</del>	<del>0</del>	0	0	0	0	0	0	7	2	5
T1	<del>2</del>	<del>0</del>	<del>0</del>	2	0	2	0	0	0			
T2	<del>3</del>	<del>0</del>	<del>3</del>	0	0	0	0	0	0			
T3	<del>2</del>	<del>1</del>	<del>1</del>	1	0	0	1	0	0			
T4	<del>0</del>	<del>0</del>	<del>1</del>	0	0	2	0	0	0			

- Find an unmarked row, mark it, and update  $W$ 
  - T0, T2, T3, T4, T1

43

## Deadlock Detection Example 2

- Five threads and three resources (none free)

	A			R			V			W		
	X	Y	Z	X	Y	Z	X	Y	Z	X	Y	Z
T0	<del>0</del>	<del>1</del>	<del>0</del>	0	0	0	0	0	0	0	1	0
T1	2	0	0	2	0	2	0	0	0			
T2	3	0	3	0	0	1	0	0	0			
T3	2	1	1	1	0	0	1	0	0			
T4	0	0	1	0	0	2	0	0	0			

Threads T1, T2, T3 & T4 in deadlock set

Cannot find a row in  $R \leq W$ !

Now wants one unit of resource Z

- One minor tweak to T2's request vector...

44

## Deadlock Recovery

- What can we do when we detect deadlock?
- Simplest solution: kill someone!
  - Ideally someone in the deadlock set ;-)
- Brutal, and not guaranteed to work
  - But sometimes the best we can do
  - E.g. linux OOM killer (better than system reboot?)
- Could also resume from checkpoint
  - Assuming we have one
- In practice computer systems seldom detect or recover from deadlock: rely on programmer

45

## Priority Inversion

- Another liveness problem...
  - Due to interaction between locking and scheduler
- Consider three threads: T1, T2, T3
  - T1 is high priority, T2 low priority, T3 is medium
  - T2 gets lucky and acquires lock L...
  - ... T1 preempts him and sleeps waiting for L...
  - ... then T3 runs, preventing T2 from releasing L!
- This is not deadlock or livelock
  - But not very desirable (particularly in RT systems)

47

## Livelock

- Deadlock is at least 'easy' to detect by humans
  - System basically blocks & stops making any progress
- Livelock is less easy to detect as threads continue to run... but do nothing useful
- Often occurs from trying to be clever, e.g.:

```
// thread 1
lock(X);
while (!tryLock(Y)) {
  unlock(X);
  yield();
  lock(X);
}
...
```

```
// thread 2
lock(Y);
...
while(!tryLock(X)) {
  unlock(Y);
  yield();
  lock(Y);
}
...
```

46

## Handling Priority Inversion

- Typical solution is **priority inheritance**:
  - Temporarily boost priority of lock holder to that of the highest waiting thread
  - Hard to reason about resulting behaviour
  - (some RT systems (like VxWorks) allow you specify on a per-mutex basis [to Rover's detriment ;-])
- Windows "solution"
  - Check if any ready thread hasn't run for 300 ticks
  - If so, double its quantum and boost its priority to 15
  - ☺

48